


## Instruction part 1 - Back

This instruction is developed from the basic dress block and the basic trouser block.  
Copy the bodice part of the basic dress block from shoulder to waistline and the basic trouser block.

Parallel to HC1, draw a guide line from the point where the waistline and the side seam meet at the trouser. Place the bodice part so the waistline of the bodice is placed along the guide line and the the CB-line of the bodice touches the CB-line of the trouser. Smooth out the CB-line of the jumpsuit from above the waistline down to HC1, so the jumpsuit will get a nice smooth CB-line.  
Draw a guide line perpendicular to the crease line at the trouser to the bottom of the trouser waist dart. Then extend the waist dart of the bodice downwards to this guide line. The original waist dart at the back trouser should no longer be used.

From the side seam of the trouser, measure 1.5 cm inwards the waistline. Through this point, draw a new side seam from SIH to HC2. Look closely at the figure and make the side seam look like that one.

On the waist line from the new side seam measure the value for X inwards to the original side seam of the bodice. This value will be used to make the front side seam on the next page.



## Instruction part 2 - Front

Parallel with HC1, draw a guide line from the point where the waistline and the side seam meet at the trouser. Draw a guide line perpendicular to HC1 that goes through the point where the trouser CF-line and waistline meet. Place the bodice part so the waistline and the CF-line of the bodice are placed along the two guides lines.

Extend the waist dart of the bodice down to HC1. The original dart at the front trouser should no longer be used.

From the side seam of the bodice, measure X cm inwards the waist line (X is measured on the back, see page 1). Through this point, draw a new side seam from SIH to HC2. Look closely at the figure and make the side seam look like that one.

Control measurements (at front and back):

Waist line =  $1/2 WC + 0$  to 0.5 cm


Headline 1 =  $1/2 HV1 + 0$  to 0.5 cm

The side seams at the front and back must have equal lengths from SIH to HV2.

Make sure that the pattern pieces match the control measurements.

The pattern pieces can now be copied. See the next page for the pattern overview.

Find sleeves for this model at [cutupstudio.com](http://cutupstudio.com)



# JUMPSUIT - Pattern overview

\*The illustrations are without scale

